

GEUTEBRÜCK

MBeg+

Firmware 3.0

Release Notes

Table of contents

Bugfixes / Changes	4
Release Notes for the Main Features	5
Key assignment control panel MBeg+.....	6

MBeg+ 3.0

Type	Modul	Detailed Description
Improvement	Mbeg+	Possibility to add 256 persistent variables (Integer, Float, Boolean, String) to "00 - ff" (.json files)
Improvement	Mbeg+	Reset of Persistent Variable
Improvement	Mbeg+	MBeg+ Factory Reset (via Telnet)
Improvement	Mbeg+	Switching back to PTZ control after entering the camera number is now customizable (.json files)
Improvement	Mbeg+	Switching characters in numboxes possible with joystick or shuttle and it is possible to switch between numboxes with jogwheel
Bugfix	Mbeg+	Send Stop command if joystick not equal to "0" ZOC (Zero On Change)
New Feature	Mbeg+	"G-Core" Layout, is selectable in MBeg+, this Layout uses the new possibilities of MBeg+ 3.0 FW and offers a few enhancements, see attached document: "Key Mapping G-Core Layout"

Release Notes for the Main Features

MBeg+ Firmware 3.0 Release Notes

We are pleased to announce the release of Geutebrück MBeg+ firmware version 3.0, which includes a number of interesting new features and improvements. This firmware update is essential for anyone who wants to use our innovative "MBeg+ Layout Editor". Moreover, it offers advanced features for configuring your MBeg+ unit with persistent variables and the ability to program an automatic return to PTZ control after entering a camera number.

In response to feedback and requests from our users, we have also developed a special standard layout for G-View that will enhance the overall operation of your MBeg+ in conjunction with G-View.


For detailed information on the new features and instructions on how to program your MBeg+, please contact our technical service team at Geutebrück.

Key assignment control panel MBeg+

F1 Maximize viewer	F2 Minimize viewer	F3 Select viewer	F4 Viewer selection
F5 Event back	F6 Event before	F7 Play	F8 Playmode Live
F9 Contact 1	F10 Contact 2	F11 Contact 3	F12 Contact 4
F13 Contact 5	F14 Contact 6	F15 Logout	F16 Setup

Device view

Front view



1	Function key's F1 to F8
2	Touch Display
3	Function key's F9 to F16
4	Jog and Shuttle Controller
5	Numeric field with delete key and enter key
6	Programmable keys for the menu function
7	Joystick with two buttons

Technical alterations reserved.

GEUTEBRÜCK GmbH

Im Nassen 7-9 | D-53578 Windhagen | Tel. +49 (0)2645 137-0 | Fax-999 | E-mail: info@geutebrueck.com | Web: www.geutebrueck.com